

MigratoryData Server

Installation Guide

Version 5.0

November 13, 2018



Copyright Information

Copyright © 2007-2018 Migratory Data Systems. ALL RIGHTS RESERVED.

THIS DOCUMENT IS PROVIDED “AS IS” WITHOUT WARRANTY OF ANY KIND, EITHER EXPRESS OR IMPLIED, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE, OR NON-INFRINGEMENT.

THIS DOCUMENT COULD INCLUDE TECHNICAL INACCURACIES OR TYPOGRAPHICAL ERRORS. CHANGES ARE PERIODICALLY ADDED TO THE INFORMATION HEREIN; THESE CHANGES WILL BE INCORPORATED IN NEW EDITIONS OF THE DOCUMENT. MIGRATORY DATA SYSTEMS MAY MAKE IMPROVEMENTS AND/OR CHANGES IN THE PRODUCT DESCRIBED IN THIS DOCUMENT AT ANY TIME.

Contents

1	Introduction	3
1.1	Release	3
1.2	Related Documents	3
2	Requirements and recommendations	4
2.1	Supported Operating Systems	4
2.2	Installation Requirements	4
2.2.1	OpenJDK	4
2.2.2	OpenSSL (Optional)	4
2.3	Hardware	5
2.3.1	CPU	5
2.3.2	RAM	5
2.4	Capacity Planning	5
3	Linux	6
3.1	RPM Based Linux	6
3.1.1	Install OpenJDK Java Runtime Environment	6
3.1.2	Install OpenSSL for Native TLS/SSL Communication	6
3.1.3	Install MigratoryData Server	6
3.1.4	Upgrade MigratoryData Server	8
3.1.5	Uninstall MigratoryData Server	8
3.2	DEB Based Linux	8
3.2.1	Install OpenJDK Java Runtime Environment	8

3.2.2	Install OpenSSL for Native TLS/SSL Communication	9
3.2.3	Install MigratoryData Server	9
3.2.4	Upgrade MigratoryData Server	10
3.2.5	Uninstall MigratoryData Server	10
4	Platform Independent	11
4.0.1	Install OpenJDK Java Runtime Environment	11
4.0.2	Install MigratoryData Server	11

1. Introduction

This guide describes the installation of MigratoryData Server. It is recommended to read *MigratoryData Architecture Guide* before reading this document for a better understanding of the concepts and to have a more comprehensive background.

1.1 Release

This guide is part of the documentation set for MigratoryData Server version 5.0.

1.2 Related Documents

- *MigratoryData Architecture Guide*
- *MigratoryData Configuration Guide*
- *MigratoryData API Developer's Guide* and *Reference Manual* for each client library of MigratoryData Server

2. Requirements and recommendations

2.1 Supported Operating Systems

Written in Java, MigratoryData Server runs on all major operating systems: Linux/Unix, Mac OS, Windows, and potentially any other platform having support for OpenJDK Java Runtime Environment (JRE) version 8 or later.

MigratoryData Server comes with 64-bit installers for RPM-based and DEB-based Linux distributions. Also, a platform-independent tarball is available.

The recommended operating systems for production deployments are Red Hat Enterprise Linux or Centos 6 or later and Debian 7 or later.

2.2 Installation Requirements

2.2.1 OpenJDK

You need to install Java Runtime Environment (JRE) version 8 or higher on your system before you can install and run MigratoryData Server.

The recommended JRE is OpenJDK version 8.

2.2.2 OpenSSL (Optional)

MigratoryData Server comes with full support for TLS/SSL communication which can be used for most deployments and for all supported platforms.

However, for Linux large deployments with lots of users, in order to make best use of the available hardware resources, MigratoryData Server can be configured to use native TLS/SSL communication provided by the OpenSSL library. The integration with OpenSSL is made via the Apache Portable Runtime (APR) library. In this way, the requirement is that you install OpenSSL and APR libraries on your system before you can use the native TLS/SSL communication. To enable the native TLS/SSL communication, add to the configuration file of MigratoryData Server:

```
Native.Ssl = true
```

2.3 Hardware

2.3.1 CPU

In a production environment it is recommended to have a server with at least 4 CPU cores, but the recommendation can grow to more CPU cores depending on the load of data on the server and how much simultaneous clients will be connected.

Note — For development or small deployments there are no special requirements concerning CPU. You can use any decent workstation hardware.

2.3.2 RAM

In a production environment it is recommended to have 8 GB or more memory depending on the load of data on the server and how much simultaneous clients will be connected.

Note — For development or small deployments it is recommended to have at least 512 MB memory.

2.4 Capacity Planning

You can estimate the hardware and the number of MigratoryData Server instances required for your use case by using *MigratoryData Benchmark Kit*, a software tool able to:

- connect a configurable number of concurrent clients
- subscribe to a configurable number of subjects per client
- publish messages of a configurable size at a configurable frequency

3. Linux

3.1 RPM Based Linux

The installation procedure described in this section has been tested on Red Hat Enterprise Linux and CentOS 64-bit distributions.

3.1.1 Install OpenJDK Java Runtime Environment

As discussed in Section 2.2.1, the Java Runtime Environment (JRE) version 8 (or later) is required for running MigratoryData Server. To install the JRE version 8 of OpenJDK, run as root:

```
yum install java-1.8.0-openjdk-headless
```

Validate your installation with the following command:

```
java -version
```

The output should be something like:

```
openjdk version "1.8.0_181"  
OpenJDK Runtime Environment (build 1.8.0_181-8u181-b13-2 deb9u1-b13)  
OpenJDK 64-Bit Server VM (build 25.181-b13, mixed mode)
```

3.1.2 Install OpenSSL for Native TLS/SSL Communication

As discussed in Section 2.2.2, the OpenSSL and APR libraries are required to enable native TLS/SSL communication. To install these libraries, run as root:

```
yum install apr openssl
```

3.1.3 Install MigratoryData Server

Download the RPM package of MigratoryData Server and run as root the following command to install it:


```
rpm -vi migratorydata-Version-Architecture.rpm
```

This will deploy MigratoryData Server as follows:

Location	Description
/etc/migratorydata/migratorydata.conf	The default configuration file. Please refer to <i>MigratoryData Configuration Guide</i> to learn how to customize it
/var/log/migratorydata/	The logs folder
/usr/share/migratorydata/	The folder which contains the object code of MigratoryData Server as a JAR file
/usr/bin/migratorydata	A script used by the <code>init.d</code> daemon script
/etc/init.d/migratorydata	The <code>init.d</code> daemon script used to start, stop, and restart the MigratoryData Server service
/usr/share/doc/migratorydata	Folder containing docs, examples, and licenses

After installation:

1. The service will start automatically when the machine reboots. To manually start, stop, restart, and get the status of the service, run as root one of the following commands:

```
/etc/init.d/migratorydata start
/etc/init.d/migratorydata stop
/etc/init.d/migratorydata restart
/etc/init.d/migratorydata status
```

2. To test the installation start a web browser on the machine where MigratoryData Server has been installed and open the following URL:

```
http://localhost:8800
```

If a browser is not available on the machine where MigratoryData Server has been installed, then, supposing the address of the machine is `push.example.com` and the port 8800 is not blocked by the firewall of the machine, you can remotely test the installation by opening the following URL from a remote machine connected to `push.example.com`:

```
http://push.example.com:8800
```

This will open the home page of MigratoryData Server which contains docs and examples.

3. The next step is to build your clients to communicate with your MigratoryData Server installation. Please refer to the *Developer's Guide* and *Reference Manual* of the client library that you intend to use to learn how to build clients for MigratoryData Server.

3.1.4 Upgrade MigratoryData Server

To upgrade MigratoryData Server to a newer version, run as root the following command:

```
rpm -vU migratorydata-NewVersion-Architecture.rpm
```

Note — The upgrade process will preserve your customized configuration files to ensure the continuity of your service. A copy of the default configuration of the new version is also provided with the extension *.rpmnew* if it differs from the default configuration of the installed version.

3.1.5 Uninstall MigratoryData Server

To remove MigratoryData Server from your system, run as root the following command:

```
rpm -ve migratorydata
```

3.2 DEB Based Linux

The installation procedure described in this section has been tested on Debian and Ubuntu 64-bit distributions.

3.2.1 Install OpenJDK Java Runtime Environment

As discussed in Section 2.2.1, the Java Runtime Environment (JRE) version 8 (or later) is required for running MigratoryData Server. To install the JRE version 8 of OpenJDK, run as root:

```
apt-get install openjdk-8-jre-headless
```

Validate your installation with the following command:

```
java -version
```

The output should be something like:

```
openjdk version "1.8.0_181"
OpenJDK Runtime Environment (build 1.8.0_181-8u181-b13-2 deb9u1-b13)
OpenJDK 64-Bit Server VM (build 25.181-b13, mixed mode)
```

3.2.2 Install OpenSSL for Native TLS/SSL Communication

As discussed in Section 2.2.2, the OpenSSL and APR libraries are required to enable native TLS/SSL communication. To install these libraries, run as root:

```
apt-get install libapr1 openssl
```

3.2.3 Install MigratoryData Server

Download the DEB package of MigratoryData Server and run as root the following command to install it:

```
dpkg -i migratorydata-Version-Architecture.deb
```

This will deploy MigratoryData Server as follows:

Location	Description
/etc/migratorydata/migratorydata.conf	The default configuration file. Please refer to <i>MigratoryData Configuration Guide</i> to learn how to customize it
/var/log/migratorydata/	The logs folder
/usr/share/migratorydata/	The folder which contains the object code of MigratoryData Server as a JAR file
/usr/bin/migratorydata	A script used by the <code>init.d</code> daemon script
/etc/init.d/migratorydata	The <code>init.d</code> daemon script used to start, stop, and restart the MigratoryData Server service
/usr/share/doc/migratorydata	Folder containing docs, examples, and licenses

After installation:

1. The service will start automatically when the machine reboots. To manually start, stop, restart, and get the status of the service, run as root one of the following commands:

```
/etc/init.d/migratorydata start
/etc/init.d/migratorydata stop
/etc/init.d/migratorydata restart
/etc/init.d/migratorydata status
```

2. To test the installation start a web browser on the machine where MigratoryData Server has been installed and open the following URL:

```
http://localhost:8800
```

If a browser is not available on the machine where MigratoryData Server has been installed, then, supposing the address of the machine is `push.example.com` and the port 8800 is not blocked by the firewall of the machine, you can remotely test the installation by opening the following URL from a remote machine connected to `push.example.com`:

```
http://push.example.com:8800
```

This will open the home page of MigratoryData Server which contains docs and examples.

3. The next step is to build your clients to communicate with your MigratoryData Server installation. Please refer to the *Developer's Guide* and *Reference Manual* of the client library that you intend to use to learn how to build clients for MigratoryData Server.

3.2.4 Upgrade MigratoryData Server

To upgrade MigratoryData Server to a newer version, run as root the following command:

```
dpkg -i migratorydata-NewVersion-Architecture.deb
```

Note — The upgrade process will preserve your customized configuration files to ensure the continuity of your service. A copy of the default configuration of the new version is also provided with the extension `.dpkg-dist` if it differs from the default configuration of the installed version.

3.2.5 Uninstall MigratoryData Server

To remove MigratoryData Server from your system, run as root the following command:

```
dpkg --purge migratorydata
```

4. Platform Independent

The installation procedure described in this section has been tested on Windows, Linux, and Mac OS platforms.

4.0.1 Install OpenJDK Java Runtime Environment

As discussed in Section 2.2.1, the Java Runtime Environment (JRE) version 8 (or later) is required for running MigratoryData Server. To install the JRE version 8 of OpenJDK, follow the specific instructions for your operating system.

4.0.2 Install MigratoryData Server

Download and extract the tarball distribution of the MigratoryData Server to any folder. You will have the following layout in your installation folder:

Location	Description
doc	Folder containing the documentation set for MigratoryData Server
html	Folder containing the home page of MigratoryData Server including documentations and examples
logs	The logs folder
THIRD-PARTY-LICENSES	Folder containing the licenses of the third-party components embedded in MigratoryData Server
LICENSE.txt	Use of MigratoryData Server is subject to the license terms defined by this file
migratorydata.conf	The default configuration file. Please refer to <i>MigratoryData Configuration Guide</i> to learn how to customize it
migratorydata.jar	The object code of MigratoryData Server
README.txt	A short introduction to the product
start-migratorydata.bat	The start script of MigratoryData Server for Windows systems
start-migratorydata.sh	The bash start script of MigratoryData Server for Linux/Unix systems

After installation:

1. To start MigratoryData Server, open a console/terminal, change to the directory where MigratoryData Server package has been extracted, and run one of the following commands according to your operating system:

```
start-migratorydata.bat    (Windows)
./start-migratorydata.sh  (Linux/Unix)
```

2. To test the installation start a web browser on the machine where MigratoryData Server has been installed and open the following URL:

```
http://localhost:8800
```

If a browser is not available on the machine where MigratoryData Server has been installed, then, supposing the address of the machine is `push.example.com` and the port 8800 is not blocked by the firewall of the machine, you can remotely test the installation by opening the following URL from a remote machine connected to `push.example.com`:

`http://push.example.com:8800`

This will open the home page of MigratoryData Server which contains docs and examples.

3. The next step is to build your clients to communicate with your MigratoryData Server installation. Please refer to the *Developer's Guide* and *Reference Manual* of the client library that you intend to use to learn how to build clients for MigratoryData Server.

